



Access Rights for PCT-SAFE Installation and Operation

January 27, 2004



**WORLD INTELLECTUAL PROPERTY
ORGANIZATION**

GENEVA

Table of Contents

- 1. INTRODUCTION4
 - 1.1 PURPOSE.....4
 - 1.2 SCOPE.....4
- 2. LIST OF REQUIREMENTS.....5
 - 2.1 INSTALLATION REQUIREMENTS5
 - 2.2 ACCESS RIGHTS REQUIREMENTS5

1. Introduction

1.1 Purpose

The purpose of this document is to summarize the access rights required for installation and proper operation of PCT-SAFE client software in various Windows platforms.

1.2 Scope

This document provides necessary explanations concerning access rights and installation requirements for the PCT-SAFE client software in the Windows NT4/2000/XP. There are no specific requirements for the PCT-SAFE client in the Windows 98/ME.

2. List of Requirements

2.1 Installation requirements

The PCT-SAFE client installation process requires *administrator privilege*, in other words, to install the PCT-SAFE client the user should login as a local administrator of the PC.

2.2 Access rights requirements

The following access rights in the registry and local hard drive should be granted for the users:

Registry key or file (or whole directory)	Accessed by Module/Interface	Permissions
HKEY_CLASSES_ROOT\CLSID\{4ECCBBFD-E55D-43F9-9135-59C8943E6F61} HKEY_CLASSES_ROOT\Interface\{129B335F-837C-477D-B946-240C28BA316C}	ClientAdvise	Full Control
HKEY_CLASSES_ROOT\CLSID\{D4535D47-30E5-48AA-9901-5B5566E90BF4} HKEY_CLASSES_ROOT\Interface\{1EF9E2A1-A05F-4237-9499-34E0802338EE} HKEY_CLASSES_ROOT\TypeLib\{0DDBDCE7-8EDD-4C1A-ACEA-69D1D83AA7CA} HKEY_CLASSES_ROOT\MComClient.GUICOMClient	MClient	Full Control
HKEY_CLASSES_ROOT\TypeLib\{F683092E-8D04-400B-87DE-F526B586E8FF} HKEY_CLASSES_ROOT\FMWIPO.GUIFMWIPOClientAdvise	Fmwipoi	Full Control
HKEY_CLASSES_ROOT\TypeLib\{55B7CCC4-39F4-4992-90CF-D168C3BA6C29} HKEY_CLASSES_ROOT\PCT.GUIPCTClientAdvise	Pctwipoi	Full Control
PCT-SAFE installation folder (including all subfolders)	Fmwipoi	Full Control
Fmwipoi.ini file in WINDOWS directory (or in WINNT directory in case of Windows NT)	Fmwipoi	Full Control
Fmwi_cl.ini file in WINDOWS directory (or in WINNT directory in case of Windows NT)	Fmwipoi	Full Control
Pctwipoi.ini file in WINDOWS directory (or WINNT directory in case of Windows NT)	Pctwipoi	Full Control